

Project Settings

Table of Contents

- [Tags](#)
- [Administration items](#)
 - [Adding a Project](#)
 - [Analysis Report Processing](#)
 - [Deleting a Project](#)
 - [Setting the Leak Period](#)
 - [Updating Project Key](#)
 - [Default Issue Assignee](#)
 - [Quality Gate and Setting Quality Profiles](#)
 - [Setting Exclusions](#)
 - [Customizing Links](#)

Tags

Project tags allow you to categorize and group projects for easier selection on the [Projects](#) page. Project tags can be administered from the project home page. Administrators will see a dropdown menu indicator next to the project's list of current tags (or next to the "No tags" indicator). If the tag you want isn't visible in the dropdown, use the built in "search" input to find what you're looking for or create it on the fly.

Administration items

Project administration is accessible through the **Administration** menu.

Only project administrators can access project settings (See [Authorization](#)).

Adding a Project

A project is automatically added at its first analysis. Note that you can also [provision projects](#).

Analysis Report Processing

A project-level Background Tasks page is available at **Administration > Tasks** to allow project administrators to check their projects' processing. It offers analysis report details and logs. See [Background Tasks](#) for more.

Deleting a Project

You can delete a project through **Administration > Deletion**:

Note also that a [projects can also be deleted in bulk](#).

Setting the Leak Period

The leak period can be set on a per-project basis through **Administration > General Settings > Leak > Leak Period**. The default value is *previous_version*, which is probably the most appropriate value for projects that version/release regularly. For other projects, a time period such as 30 days (enter "30", the "days" part is understood) may be more appropriate.

Note that this can be set at the global level as well.

Updating Project Key

The project key can be updated (without losing the history on the project) at **Administration > Update Key**.

The new key must contain at least one non-digit character. Allowed characters are: 'a' through 'z', 'A' through 'Z', '-' (dash), '_' (underscore), '.' (dot), ':' (colon) and digits '0' to '9'.

Default Issue Assignee

When new issues are created during an analysis, they are assigned to the last committer where the issue was raised. When it is not possible to identify the last committer, issues can be assigned to a default assignee, at **Administration > General Settings > Issues**.

Quality Gate and Setting Quality Profiles

Project administrators can select which:

- Quality profiles (go to **Administration > Quality Profiles**)
- Quality gate (go to **Administration > Quality Gate**)

to use on their project.

Setting Exclusions

See [Narrowing the Focus](#).

Customizing Links

On top of standard links which may only be set as [Analysis Parameters](#), additional custom links can be added through the web interface (under **Administration > Links**). Those links will then be displayed in the [Project Page](#).